



Sophos iView V03.01.1 GA Release Notes

Document Date: July 2017

Contents

Sophos iView SIV OS v 03.01.1 GA.....	3
Note.....	3
Overview	3
Applicable iView versions	3
Supported Device type and versions	3
Features.....	3
Bug Fixes	4
Supported Languages	5
Download Information.....	5
Feedback	6

Sophos iView SIV OS v 03.01.1 GA

Release Type: GA

Julys, 2017

Note

Device reboots after the upgrade.

Overview

The GA release for Sophos iView 03.01.1 (Build 313) includes features, enhancements and bug fixes.

Applicable iView versions

The following iView versions can be upgraded to this release:

- SIV OS 02.00.00 (GA release – Build 092)
- SIV OS 02.00.00 MR-1 (Build 306)
- SIV OS 02.00.00 MR-2 (Build 776)
- SIV OS 03.01.1 Beta (Build 198)

Supported Device type and versions

- Sophos Firewall OS: Sophos Firewall OS 15.01.0 and above
- Sophos UTM 9: Sophos UTM 9.3 and above
- CyberoamOS: CyberoamOS 10.6.1 MR-3 and above

Features

1. Improved UX / UI
 - Improved layout and navigation that aligns with SFOS v16 and provides a more user friendly approach.
 - Better user experience to select devices and groups.
2. Log Digester

- iView support for importing UTM 9.4x logs to generate reports for Sophos UTM.
3. Data Anonymization
 - Support data anonymization in iView to meet privacy requirements in Europe region.
 4. Reports for SFOS devices
 - a. Missing Heartbeat Reports
 - b. Web Reports
 - Web Activity Reports
 - Warned Summary Reports
 - c. Appropriate labels instead of NA in reports
 - d. Sandstorm Reports
 5. Reports for UTM devices
 - Web User Group Report
 6. Download reports with sorting criteria applied from UI
 7. PDF Reports
 - Improved widget graphics and template
 - Downloaded reports with sorting criteria applied from UI

Bug Fixes

- LDAP Authentication: GUI validation for password field missing. [NCR-2613]
- When integrated with LDAP for iView administrator authentication, the administrator LDAP password is visible as text in iView log files. [NCR-2539]
- Configuration backup over FTP does not work. [NCR-2667]
- Single Sign-on from SFM to iView is not working for users other than Super administrator. [NCR-2588]
- User is able to set password using special characters "11+β()1f1,-A1111ÖÄÜ" in iView but not able to login using the same password. [NCR-2060]
- iView WebAdmin when accessed over HTTPS: Audit logs not displayed. [NCR-1806]
- Detail WebUser Reports: Records not displayed in some cases. [NCR-2290]
- Keyword search in Search Engine Reports does not display records. [NCR-2615]
- Sophos iView does not log blocked application attempts for some rules. [rule 60019] [NCR-2600]

- Email usage report does not display records. [NCR-2209]
- Unicode content not displayed. [NCR-2084]
- Scheduled Executive Report: Report data not displayed. [NCR-1824]
- Unable to resume a paused log digestion process after navigating to other page on UI. [NCR-2712]

Supported Languages

- English

Download Information

Sophos Up2Date technology makes it easy for you to upgrade your Sophos iView v2 to the latest version.

You can use two methods to apply the available Up2Date package to the system:

- Method 1
 - Log in to your iView web interface.
 - Go to System > Maintenance > Firmware.
 - Click “Check for new Firmware” to download the latest firmware.
 - Once it is downloaded, click “Install” to begin the install. The system will reboot and the new firmware is installed.
 - You can roll back to the previous firmware version by clicking “Boot Firmware” against the non-active firmware. Any configuration changes made between the upgrade and roll back will be lost.
- Method 2
 - Download the Up2Date package from [MySophos](#).
 - Go to System > Maintenance > Firmware.
 - Select “Upload firmware” against the non-active firmware to upload the new firmware file and click “Upload & Boot”. The system will reboot and the new firmware is installed.
 - You can roll back to the previous firmware version by clicking “Boot Firmware” against the non-active firmware. Any configuration changes made between the upgrade and roll back will be lost.

Note: You must click **Check For New Firmware** option to upgrade your iView Beta [03.01.1.198] to iView GA [03.01.1.313].

Feedback

- If you want to provide feedback or want to discuss any of the iView features you can post it on our [community boards](#). Please indicate the version you are using to help us (and everyone helping you).
- If you have any feedback on our help, manual, or any documentation (Online Help) please send it to nsg-documentations@sophos.com.
- For any questions or comments regarding this release, please see our online forums for more information.